## **NETWORK ADDRESS TRANSLATION**

## packetlife.net

Technet24

Example Topology	packetilite.n			
	Example Topology Address Classification			
	Inside Local An actual address assigned to an inside host			
	nside Global An inside address seen from the outside			
FastEthernet0 FastEthernet1 Out	<b>Itside Global</b> An actual address assigned to an outside host			
	utside Loca	An outside ac the inside	An outside address seen from the inside	
NAT Boundary Configuration	Perspective			
interface FastEthernet0 ip address 10.0.0.1 255.255.0.0 ip nat inside		Local	Global	
	Inside	Inside Local	Inside Global	
interface FastEthernet1 ip address 174.143.212.1 255.255.252.0 ip nat outside	Outside	Outside Local	Outside Global	
Static Source Translation	Terminology			
! One line per static translation ip nat inside source static 10.0.0.19 192.0.2.1 ip nat inside source static 10.0.1.47 192.0.2.2	<b>NAT Pool</b> A pool of IP addresses to be used as inside global or outside local addresses in translations			
ip nat outside source static 174.143.212.133 10.0.0.47 ip nat outside source static 174.143.213.240 10.0.2.181	An extensior	ss Translation (PAT) to NAT that translates information		
Dynamic Source Translation	at layer four and above, such as TCP and UDP port numbers; dynamic PAT configurations include the <b>overload</b> keyword			
<pre>! Create an access list to match inside local addresses access-list 10 permit 10.0.0.0 0.0.255.255 ! ! Create NAT pool of inside global addresses ip nat pool MyPool 192.0.2.1 192.0.2.254 prefix-length 24</pre>	<b>Extendable Translation</b> The <b>extendable</b> keyword must be appended when multiple overlapping static translations are configured			
! ! Combine them with a translation rule	Special NAT Pool Types Rotary Used for load balancing		l Types	
ip nat inside source list 10 pool MyPool				
<pre>     Dynamic translations can be combined with static entries     ip nat inside source static 10.0.0.42 192.0.2.42 </pre>	Match- Preserves the host portion of Host the address after translation			
Port Address Translation (PAT)	Troubleshooting			
	show ip nat translations [verbose]			
! Static layer four port translations	show ip nat statistics			
ip nat inside source static tcp 10.0.0.3 8080 192.0.2.1 80	clear ip nat translations			
	clear ip r	nat translatio	ons	
ip nat inside source static tcp 10.0.0.3 8080 192.0.2.1 80 ip nat inside source static udp 10.0.0.14 53 192.0.2.2 53		nat translations		
<pre>ip nat inside source static tcp 10.0.0.3 8080 192.0.2.1 80 ip nat inside source static udp 10.0.0.14 53 192.0.2.2 53 ip nat outside source static tcp 174.143.212.4 23 10.0.0.8 23 ! ! Dynamic port translation with a pool</pre>	NA ip nat trar ip nat trar	<b>T Translations</b>	<b>Tuning</b> meout <seconds> meout <seconds></seconds></seconds>	
<pre>ip nat inside source static tcp 10.0.0.3 8080 192.0.2.1 80 ip nat inside source static udp 10.0.0.14 53 192.0.2.2 53 ip nat outside source static tcp 174.143.212.4 23 10.0.0.8 23 ! ! Dynamic port translation with a pool ip nat inside source list 11 pool MyPool overload ! ! Dynamic translation with interface overloading</pre>	NA ip nat trar ip nat trar ip nat trar	<b>T Translations</b> Islation tcp-ti Islation udp-ti	<b>Tuning</b> meout <seconds> meout <seconds></seconds></seconds>	

ip nat pool LoadBalServers 10.0.99.200 10.0.99.203 prefix-length 24 type rotary

! Enable load balancing across inside hosts for incoming traffic ip nat inside destination list 12 pool LoadBalServers

ļ.